


## To set up a Windows Mobile 6.1 PDA w/ HTC Email Powered by Google™


1. Click 'Start'.




2. Click 'Messaging'.




3. Click 'Setup E-mail'.




4. Enter email address and password, then click 'Next'.



5. Click 'Next'.



6. Click 'Next'.



7. Navigate right on device navigation box to reach 'Internet e-mail'. Then click 'Next'.

**E-mail Setup** abc 3G

**Your e-mail provider:**

Internet e-mail ◀ ▶

Your Internet service provider (ISP) or webmail provider supports POP or IMAP e-mail. If unsure, contact your provider.

Previous Next

8. Enter customer name, and click 'Next'.

**E-mail Setup** abc 3G

**Your name:**

Customer Name

(Example: Kevin Cook)

**Account display name:**

sccoast.net

The name for this account on this device.

Previous Next

9. Enter 'Incoming mail server' as pop.gmail.com. Then click 'Next'.

**E-mail Setup** abc 3G

**Incoming mail server:**

pop.gmail.com

If unsure, check with your provider to get POP/IMAP settings.

**Account type:**

POP3 ◀ ▶

Previous Next

10. Enter complete sccoast.net email address as 'User name'. Password should already be populated. Click 'Next'.

**E-mail Setup** abc 3G

**User name:**

customer@sccoast.net

(Examples: kevinc, domain\kevinc, kevinc@contoso.com, etc.)

**Password:**

\*\*\*\*\*

Save password

Previous Next

11. Enter 'Outgoing mail server' as cwmx.com. Then navigate down and click 'Advanced Server Settings'.

**E-mail Setup** abc 3G

**Outgoing (SMTP) mail server:**

cwmx.com

Outgoing server requires authentication

Use the same name and password for sending e-mail

[Advanced Server Settings](#)

Previous Next

12. Check the box for 'Require SSL for Incoming e-mail'. Then click 'Done'.

**E-mail Setup** abc 3G

**Advanced Server Settings**

Require SSL for Incoming e-mail

Require SSL for Outgoing e-mail

**Network connection:**

The Internet ◀ ▶

Done Cancel

13. Back on the 'Outgoing mail server' screen, click 'Next'.

**E-mail Setup** abc 3G

**Outgoing (SMTP) mail server:**

cwmx.com

Outgoing server requires authentication

Use the same name and password for sending e-mail

[Advanced Server Settings](#)

Previous Next

14. Navigate left or right to adjust how often the device should automatically check for new email. To complete email setup, click 'Finish'.

**E-mail Setup** abc 3G

Setup is complete. To download e-mail, click Finish.

**Automatic Send/Receive:**

Every 15 minutes ◀ ▶

[Review all download settings](#)

Previous Finish